

# WiseImage X for AutoCAD Installation

## System Requirements

To work with the program you need the following:

- A computer that meets the requirements of AutoCAD version 2000/2000i/2002/2004/2005/2006 or AutoCAD LT 2002/2004/2005/2006;
- AutoCAD 2000 or 2000i or 2002 or 2004 or 2005 or 2006; AutoCAD LT 2002 or LT 2004 or LT 2005 or LT 2006;
- Hard disk with 70 MB of free space.

## Software or Hardware Protection

WiseImage uses a software or hardware protection system. It offers the flexibility to use the program in a single user or in a network environment. To use WiseImage you need to set up the license for the program. The procedure of obtaining and setting up the license is described in the Installation chapter.

## Installation

1. Insert the WiseImage CD ROM in the corresponding drive. If the autostart function of your computer is on, the dialog box showing the program product list will be displayed.
2. To open the installation dialog manually, start the SETUP.EXE file from the CD ROM root folder.
3. Select an appropriate product from the list.
4. At first you will see the WiseImage image, then the Customer Information dialog box.
5. Enter your name in the User Name box, then enter your organization name in the Company Name box, and enter the serial number of your product copy in the Serial Number box. Check the information entered is correct at this stage, as you will not be able to change it after the installation has been completed. Click the Next button to continue. The Choose Destination Location box will appear.
6. Select AutoCAD versions to install WiseImage
7. Next you need to specify the folder name and the location, where WiseImage will be installed. You can accept the default path or specify a location for the installation with the Browse button. Click the Next button to continue.
8. Select the name of the existing AutoCAD profile, which will be used as a base to create a new WiseImage profile. After selecting the profile, click the Next button (not for LT version).
9. After selecting the type of installation, the Select Program Folder box will appear prompting for the folder name of the system menu where there

will be a shortcut for starting WiseImage. You can accept the default by clicking the Next button. If you want to change this name, enter the new Program Folder name and then click the Next button.

10. The *Setup Status* box will then appear and the copying of the WiseImage files to your computer will begin. After the copying is completed, you can start the program from the folder in the system menu with the name you specified in the previous dialog.

The installation program creates on the hard disk a folder for the WiseImage program where all necessary files are copied and it places a shortcut for WiseImage in the Windows system menu.

## Licensing

After the installation is completed, you will need to obtain a license to use WiseImage. This is done with the help of the Registration Wizard. The wizard will guide you in your installation whether it is a single-user installation or an installation on a network. Depending on the installation type you might get additional information also by e-mail about using your license. Additional information can also be found in the User's Guide.

To setup the license for the first time you have to use the *Registration Wizard*.

- Click Start on the taskbar; then choose Programs.
- Click WiseImage; then choose the Registration Wizard menu item.
- If you version is hardware locked, then attach the hardware lock in the printer or USB port of your computer before proceeding with the Registration Wizard. (Note: If you are using Windows NT or Windows 2000/XP and a hardware lock, then you must have the SENTINEL driver installed. This can be found on the WiseImage installation disk.)
- If you have already got a license, then choose the radio button entitled 'Activate license' and follow the instructions to attach your license file.

Otherwise, you should check the radio button 'Request license'. You will be led step by step through the procedure to request a license. Follow these instructions. It is recommended to make the request online or by e-mail; optionally, you can print out the request details and fax it to CSoft. The other option (Save License Request) just saves the registration details and does not make a license request.

## WiseImage Menus

The WiseImage menu can be arranged in two different ways. The default way is to create an extra menu bar. In this case, when starting AutoCAD from WiseImage, six supplementary pull-down menus are added to the standard AutoCAD menu bar, namely: rFile, rEdit, rImage, rFilter, rConvert, and rHelp.

Alternatively, only one pull-down cascade menu, WiseImage, is added to the AutoCAD menu bar. The cascade menu consists of six items: File, Edit, Image, Filter, Convert, and Help.

When you choose any item, the cascade submenu opens (identical to the corresponding pull-down WiseImage menu).

You can change from one menu structure to the other, using the MENULOAD AutoCAD command.

To change to the cascade menu

1. Enter menuload on the command line or select Customize Menus from the Tools menu of AutoCAD.
2. From the Menu Groups list choose WiseImage. Then choose Unload.
3. Select MNU extension from Files of Type. Choose COMPACT.MNU file. Click Open.

To return to the menu bar, choose LARGE.MNU file.

4. Click the Load button. Then choose Close.

To change menu items, edit the LARGE.MNU and COMPACT.MNU files located in the WiseImage root folder.