

# WiseImage X Installation

## System Requirements

To work with the program you need the following:

- Pentium processor
- 256 MB RAM
- Microsoft Windows NT 4 / 2000 / ME / XP
- Hard disk with 80 MB of free space.

## Software or Hardware Protection

WiseImage uses a software or hardware protection system. It offers the flexibility to use the program in a single user or in a network environment. To use WiseImage you need to set up the license for the program. The procedure of obtaining and setting up the license is described in the Installation chapter.

## Installation

1. Insert CD-ROM with the WiseImage in the CD-ROM drive. If the auto start function of your computer is on, the dialog box of the program product list will be displayed.
2. To open the installation dialog manually, start the SETUP.EXE file from the CD ROM root folder.
3. Select an appropriate product from the list.
4. You will see the WiseImage 6 image first, then the *Customer Information* dialog box.
5. Enter your name into the *User Name* box, then enter your organization name into the *Company Name* box, and enter the serial number of your product copy from software CD-ROM or Box into the *Serial Number* box. Check the correctness of the information entered, as after the installation is completed, there is no possibility to change these data. Click on the *Next* button to continue. The *Choose Destination Location* box will appear.
6. It specifies the folder name and the disk, where the WiseImage program will be installed. You can accept the default path or specify a location for the installation to be made with the *Browse* button. Click on the *Next* button to continue.
7. You can change a type of installation in the displayed box. If you do not want to make changes, click on the *Next* button. The Program and the example files will be installed. If you do not want to install examples files, select the *Compact* type and click on *Next*. The product can have other types of installation depending on its version. Their description is provided in the lower box of the dialog box.
8. After selecting a type of installation, the *Select Program Folder* box will appear prompting to change the folder name of the system menu where there will be a shortcut of WiseImage start. The *Program Folders* already has a name, which you can accept by clicking on the *Next* button. If you want to change this name, enter another one and then click on the *Next* button.

9. The Setup Status box will appear and the copying of the WiseImage files on the computer will begin. After the copying is completed, you can start the program from the folder to the system menu with the name you specified in the previous dialogue.

The installation program creates on the hard disk a folder for the WiseImage program where all necessary files are copied and it places a shortcut for WiseImage in the Windows system menu.

### **Licensing**

After the installation is completed, you will need to obtain a license to use WiseImage. This is done with the help of the Registration Wizard. The wizard will guide you in your installation whether it is a single-user installation or an installation on a network. Depending on the installation type you might get additional information also by e-mail about using your license. Additional information can also be found in the User's Guide.

To setup the license for the first time you have to use the *Registration Wizard*.

- Click Start on the taskbar; then choose Programs.
- Click WiseImage; then choose the Registration Wizard menu item.
- If your version is hardware locked, then attach the hardware lock in the printer or USB port of your computer before proceeding with the Registration Wizard. (Note: If you are using Windows NT or Windows 2000/XP and a hardware lock, then you must have the SENTINEL driver installed. This can be found on the WiseImage installation disk.)
- If you have already got a license, then choose the radio button entitled 'Activate license' and follow the instructions to attach your license file.

Otherwise, you should check the radio button 'Request license'. You will be led step by step through the procedure to request a license. Follow these instructions. It is recommended to make the request online or by e-mail; optionally, you can print out the request details and fax it to CSoft. The other option (Save License Request) just saves the registration details and does not make a license request.